#### **Product Overview**

ProteanFectTM Transfection Kit offers a non-viral, non-electroporation, and non-liposomal transfection system utilizing engineered mammalian proteins. This innovative design achieves high transfection efficiency while maintaining a superior safety profile. Specifically developed for hard-to-transfect cell lines, the kit ensures robust performance across a broad range of cell types (refer to Table 4). Additionally, it excels in delivering high molecular weight nucleic acids and co-transfecting multiple nucleic acids.

### **Component Description**

The kit is shipped on dry ice. Once received, store the components as indicated below. The kit includes positive control samples with EGFP-encoding mRNA and pDNA (plasmid DNA) to verify transfection efficiency.

**Table 1 Storage Conditions for the Components** 

Component	Storage
Reagent A	2-8°C
Reagent B	-20°C
EGFP mRNA (1 µg/µL)	-80°C
GFP pDNA (0.5 μg/μL)	-20°C

Note: Avoid repeated freeze-thaw cycles of Reagent B, EGFP mRNA, and EGFP pDNA.

### **Pre-Experimental Preparation**

**Cell Condition**: Ensure cells are in optimal physiological condition on the day of transfection, with >90% viability.

**Reagent:** Allow Reagents A and B to reach room temperature. Briefly mix each reagent by inverting or vortexing prior to use.

**Medium:** Use Opti-MEM as the recommended medium. Serum-free RPMI 1640 or DMEM can be used as alternatives. Pre-warm the medium to 37°C or room temperature before use.

# PT01-ProteanFect<sup>™</sup> Transfection Kit: Instructions for Use

### **Transfection Procedure**

### Table 2Transfection Protocol for mRNA per Well of a 96-Well Plate

Steps	Instructions for Cell Lines			
1. Transfection Complex Preparation a				
1.1 Mix Reagent A with mRNA	Mix 0.5 μg of mRNA with 40 μL of Reagent A.			
1.2 Add Reagent B	Note: Invert the Reagent A briefly before use to ensure uniformity.			
2. Cell Preparation	Add 1.4 µL of Reagent B to the mixture. Mix gently by pipetting up and down 20-30 times or vortexing for 10 seconds.			
2. Cell Freparation				
	Harvest the cells by centrifugation at 300 $g$ for 5 minutes. Discard the supernatant and wash cells once with Opti-MEM. Resuspend cells with Opti-MEM			
2.1 Suspension cells	and adjust concentration to 5×10 <sup>6</sup> - 1×10 <sup>7</sup> cells/mL.			
	Note: Avoid including FBS in the transfection medium.			
	Maintain 50%-80% cell confluence. Remove medium, wash cells once with Opti-MEM, then add 20 μL of Opti-MEM.			
2.2 Adherent cells	Note: Avoid including FBS in the transfection medium.			
	<b>Optional:</b> Harvest cells by trypsinization, then resuspend them in Opti-MEM at a concentration of 5×10 <sup>6</sup> - 1×10 <sup>7</sup> cells/mL for subsequent transfection.			
3. Transfection				
3.1 Mix transfection complex with cells	For suspension cells, mix 40 µL of transfection complex with 20 µL of cell suspension and gently pipet up and down 2-3 times. For adherent cells, a directly to the cells.			
3.2 Incubation	Incubate the cells with the transfection complex for 45-60 minutes in a cell culture incubator.			
	Terminate the reaction by adding ≥200 µL of culture medium (10X cell suspension), centrifuge at 300 g for 5 minutes, and discard the supernatant.			
3.3 Termination	For adherent cells, replace the transfection mixture with ≥200 µL of culture medium (10X cell suspension).			
	Note: The cell pellet may adhere to the tube walls. Gently remove the supernatant to minimize cell loss.			
3.4 Post-transfection culture	Incubate the transfected cells in culture medium and assess transfection efficiency after 5 to 48 hours, or at an appropriate time.			

FBS, Fetal bovine serum. **a.** The transfection complex may become slightly viscous during preparation. It can be directly added to cells once prepared without incubation. For optimal results, use the complex within 30 minutes.

Email: <u>aurorabohsales@gmail.com</u>

**Table 3 Transfection Guidelines for Different Culture Formats** 

Components	Culture Vessels a		Cell Lines		
	96-well		40 μL		
	48-well		80 μL		
Reagent A	24-well		200 μL		
•	12-well		600 μL		
	6-well		800 μL		
Nucleic Acids b		DNA	mRNA	siRNA	
	96-well	0.4 μg	0.5 μg	40 pmol	
	48-well	0.8 µg	1 µg	80 pmol	
	24-well	2 μg	2.5 µg	200 pmol	
	12-well	6 μg	7.5 µg	600 pmol	
	6-well	8 µg	10 μg	800 pmol	
Reagent B	96-well	1 μL	1.4 µL	1.4 µL	
	48-well	2 μL	2.8 µL	2.8 µL	
	24-well	5 μL	7 μL	7 μL	
	12-well	15 µL	21 µL	21 µL	
	6-well	20 μL	28 μL	28 µL	
	96-well		1×105 ~2×105 (20 μL)		
Recommended Cell Number (Opti-MEM) c	48-well	2×105 ~4×105 (40 μL)			
	24-well		5×105 ~1×106 (100 μL)		
	12-well	1.5×106 ~3×106 (300 µL)			
	6-well		2×106 ~4×106 (400 μL)		

**a.** For large-scale transfections, such as in 48-well plates or larger formats, it is recommended to use centrifuge tubes for the transfection process. **b.** When co-transfecting multiple nucleic acids, please ensure the total amount of nucleic acids added matches the recommended quantities for each plate format, as outlined in Table 3. **c.** The recommended cell number is primarily for suspension cells. For adherent cells, please adjust the cell number based on confluency.


3/6


Email: aurorabohsales@gmail.com

## Table 4 Cell Lines Successfully Transfected Using ProteanFect™ Transfection Kit

Cell Lines	Tested Nucleic Acid Types for Transfection	
Jurkat T (human T lymphoblastic leukemia cells)	pDNA, mRNA, siRNA	
LX-2 (human hepatic stellate cells)	pDNA, mRNA, siRNA	
HepG2 (human liver tumor cells)	pDNA, mRNA, siRNA	
THP-1 (human acute monocytic leukemia cell line)	mRNA, siRNA	
Raji (human Burkitt's lymphoma cells)	mRNA, siRNA	
K562 (human chronic myeloid leukemia cells)	pDNA, mRNA, siRNA	
MOLT-16 (human T lymphoblastic leukemia cells)	mRNA, siRNA	
SH-SY5Y (human neuroblastoma cells)	pDNA, mRNA, siRNA	
U2OS (human osteosarcoma cells)	pDNA, mRNA, siRNA	
U937 (human lymphoma cell line)	mRNA, siRNA	
HFF (human foreskin fibroblasts)	pDNA, mRNA, siRNA	
HEK-293 (human embryonic kidney cell line)	pDNA, mRNA, siRNA	
MC38 (mouse colon cancer cells)	mRNA, siRNA	
RAW264.7 (mouse mononuclear macrophage leukemia cells)	mRNA, siRNA	
LLC (mouse Lewis lung cancer cells)	pDNA, mRNA, siRNA	
C2C12 (mouse myoblasts)	pDNA, mRNA, siRNA	
COS7 (African green monkey kidney fibroblast-like cells)	pDNA, mRNA, siRNA	
2 2 2 1 ( India grant mana) manay		

### **Supporting Data**





### Frequently Asked Questions (FAQs) and Troubleshooting Guide

### 1. Low Transfection Efficiency

#### 1.1 Optimize Transfection Parameters

Optimize transfection parameters for each cell type. **Extend incubation time**: Adjust the incubation time of the transfection complex with cells. The maximum incubation time is 2 hours for cell lines, and 30 minutes for primary cells. **Increase ProteanFect transfection complex**: Consider increasing the amount of transfection complex to improve transfection efficiency.

### 1.2 Improve Plasmid DNA quality

Transfection efficiency is highly dependent on the quality of the plasmid DNA.

Endotoxin-free: Use an endotoxin-free kit to prepare plasmid DNA. Optimal concentration: Ensure an OD260/280 ratio between 1.7 and 1.9, and dilute DNA to 0.5–2 μg/μL using nuclease-free water.

### 1.3 Improve Cell Condition

For cell lines, transfect cells with >90% viability, confirmed by trypan blue exclusion.

Avoid using cells beyond 15 passages, and allow 2-3 passages for recently thawed cells to stabilize before transfection.

#### 1.4 Use Positive Control

We recommend using a 96-well plate format to optimize transfection conditions for a specific cell type, with EGFP mRNA as the positive control.

### 2. Low Cell Viability

Transfected cells may exhibit transient changes in behavior, but typically, viability should be restored by the second day post-transfection.

#### 3. Lack of Pellet Post-Centrifugation

In 96-well formats, it is common for the pellet to be less distinct and may adhere to the tube walls. Gently pipetting can help minimize cell loss.

**Contact Information:** For further questions, please contact us at: aurorabohsales@gmail.com